


JANOME

Quilt Maker Pro 18 VERSA

SOFTWARE UPDATE



Software Update for the Janome Versa Sit Down (Version S19)

File name: sensorS19

NOTE: After saving the update file to the USB stick, please install the USB stick in the display (on the right side) **PRIOR** to turning on the machine, then proceed with the update.

[Download Update](#)

DIRECTIONS:

- Select Tool Icon
- Select Update
- Select the sensor icon on the bottom of screen (there will be three (3) icons: Machine, Display and Sensor)
- After finishing the update power down the machine and power back up

RELEASE NOTES:

- Added automatic Com Port detection for Versa
- Improved Communication speed between machine and stitch regulation sensors
- Improved image quality detection of stitch regulation sensors.
- Added stitch regulation filter to improve regulation
- Added support for new QF01501 analog foot petal
- Fixed status reporting to machine to indicate foot petal type

JANOME

Reliability by Design